
Apply the Time–Dependent ACIS Gain Correction



CIAO 3.4 Science Threads

Table of Contents

- <u>Background Information</u>
- <u>Get Started</u>
 - <u>Related acis process events threads</u>
- <u>Generate A New Level=1 Event File</u>
 - <u>Determine the eventdef parameter</u>
 - <u>Run acis process events</u>
- Examining the Output
- <u>Summary</u>
- Parameter files:
 - ♦ <u>acis process events</u>
- <u>History</u>

URL: http://cxc.harvard.edu/ciao/threads/acistimegain/

Apply the Time–Dependent ACIS Gain Correction

CIAO 3.4 Science Threads

Overview

Last Update: 31 Mar 2008 – updated for CALDB 3.4.3: new –120 C TGAIN files and first –110 C TGAIN file

Synopsis:

The tool acis_process_events includes a time-dependent gain adjustment. This adjustment is necessary because the "effective gains" of the detectors are drifting with time as the result of an increasing CTI. The correction for this problem became part of standard data processing (SDP) in DS 7.3.1.

Purpose:

To generate a new level=1 event file with the time-dependent gain adjustment applied.

Read this thread if:

- you are working with a -120 C ACIS observation (imaging or grating) that took place after February 2000; see the <u>Background Information</u> section for details. <u>Get Started</u> shows how to check the temperature of your observation.
- you are working with a -110 C ACIS observation (imaging or grating) which uses the back-illuminated chips (ACIS-S1 and S3).

Data taken since February 2000 may need to be reprocessed to apply newer TGAIN calibration. Read the <u>Calibration Updates</u> for a history of TGAIN calibration changes.

Users interested in CCD spectroscopy should apply the T_GAIN adjustment. Grating spectroscopy may benefit marginally, in the form of improved order sorting. It is not necessary to apply this adjustment if you are only doing timing or imaging analysis, but it will not have a negative effect, either.

Calibration Updates:

- <u>CALDB v3.4.3</u> (31 Mar 2008): New time-dependent gain calibration files for 01 November 2007 31 January 2008 (Epoch 32) were added to the CALDB. A TGAIN correction for the back-illuminated chips (S1 and S3) at the -110 C focal plane temperature has also been released for the first time. The <u>CALDB 3.4.3 section</u> of the CIAO release notes explains how the files will affect your analysis.
- <u>CALDB v3.4.2</u> (14 Dec 2007): New time-dependent gain calibration files for 01 August 2007 31 December 2007 (Epoch 31) were added to the CALDB. The <u>CALDB 3.4.2 section</u> of the CIAO release notes explains how the files will affect your analysis.
- <u>CALDB v3.4.1</u> (14 Sep 2007): New time-dependent gain calibration files for 01 May 2007 31 July 2007 (Epoch 30) were added to the CALDB. The <u>CALDB 3.4.1 section</u> of the CIAO release notes explains how the files will affect your analysis.

- <u>CALDB v3.4.0</u> (16 May 2007): New time-dependent gain calibration files for 01 August 2006 31 October 2006 (Epoch 28) and 01 February 2007 – 30 April 2007 (Epoch 29) were added to the CALDB. The <u>CALDB 3.4.0 section</u> of the CIAO release notes explains how the files will affect your analysis.
- <u>CALDB v3.3.0</u> (18 Dec 2006): New time-dependent gain calibration files were added to the CALDB. Only calibration for the BI chips (S1, S3) has changed in this file; calibration for the FI chips is identical to the v5 file. The <u>How CIAO 3.4 and CALDB 3.3.0 Affect Your Analysis</u> section of the CIAO release notes explains how the files will affect your analysis.
- <u>CALDB v3.2.4</u> (7 Nov 2006): New time-dependent gain calibration files for February-April 2006 (Epoch 25) and May-August 2006 (Epoch 26) were added to the CALDB. Three existing TGAIN files were updated as well; the <u>How CALDB 3.2.4 Affects Your Analysis</u> section of the CIAO release notes explains how the files will affect your analysis.
- <u>CALDB v3.2.2</u> (15 May 2006): New time-dependent gain calibration files for May to November 2005 (epochs 23 and 24) were added to the CALDB.
- <u>CALDB v3.2.0</u> (21 Nov 2005): New higher-spatial density T_GAIN corrections for all ACIS chips were released. The <u>CIAO 3.3 release notes</u> explain how they will affect your analysis.
- <u>CALDB v3.1.0</u> (23 Jun 2005): New time-dependent gain calibration files for August to November 2004 (epoch 20) were added to the CALDB. These files include calibration for the S0, S4, and S5 ACIS chips; prior to this release, an adjustment for those chips was unavailable.
- <u>CALDB v2.29</u> (19 Nov 2004): New time-dependent gain calibration files for February, May, and August 2004 (epochs 18 and 19) were added to the CALDB.
- <u>CALDB v2.27</u> (7 Jul 2004): The calibration files necessary to apply the time-dependent gain correction were released.

Related Links:

- Analysis Guide: ACIS Data Preparation
- Why topic: ACIS Time-dependent Gain
- <u>Corrections for Time-dependence of ACIS Gain</u>: a calibration page that explains technical details of the gain adjustment.

Proceed to the <u>HTML</u> or hardcopy (PDF: <u>A4 / letter</u>) version of the thread.

Background Information

As of CALDB 3.3.0, there is *CTI calibration data* for the *entire* ACIS detector (chips I0–3 and S0–5).

As of CALDB 3.1.0, there is *time-dependent gain calibration* data for the *entire* ACIS detector (chips I0–3 and S0–5).

As of CALDB 3.4.3, there is TGAIN correction for the back–illuminated chips at the -110 C focal plane temperature. There is no CTI correction for -110 C data.

When you run acis_process_events with apply_cti=yes and apply_tgain=yes as in this thread, the CTI adjustment is done (if available) and then the time-dependent gain is calibrated.

Get Started

Sample ObsID used: 1838 (ACIS-S, G21.5-09)

File types needed: evt1; flt1; bpix1

If you created a new bad pixel file by running the <u>Create a New ACIS Bad Pixel File: Identify ACIS Hot Pixels</u> and <u>Cosmic Ray Afterglows thread</u>, use that file in this analysis. Otherwise, use the bpix1.fits file from the Archive.

This thread must be run on the level=1 event file, regardless of whether you are working with imaging or grating data. This is because one of the columns generated is PHA_RO, which is the summed value of PHA *without* the CTI and time–dependent gain adjustments applied.

There are several pieces of information we need to get from the file header before proceeding:

- *Focal plane temperature (FP_TEMP keyword)*: the gain adjustment only applies to data taken at -120 C (153 K). See this FAQ for more information on checking the temperature of your observation.
- *Observation Date (DATE-OBS keyword)*: since the gain adjustment is calibrated for several periods since February 2000, it may improve the quality of any observation done after that time.
- *If the CTI correction has been applied (CTI_CORR and/or CTI_APP keyword)*: the CTI correction may have been applied in SDP or during previous CIAO analysis. The CTI_APP header keyword was added at CIAO 3.4 and DS 7.6.10 (see the <u>ACIS CTI Correction why topic</u> for more information); the older CTI_CORR keyword is retained for backward–compatibility.
- *If the time-dependent gain correction has been applied (TGAINCOR keyword)*: if this keyword does not exist, the correction has not yet been done. Additionally, if the keyword exists, but has any value other than "T" (TRUE), the correction has not been applied. We can also check the ASCDSVER header keyword to see if the data were processed before or after this correction was added to SDP.

The tool<u>dmkeypar</u> is used to get the header information:

```
unix% dmkeypar acisf01838_000N001_evt1.fits FP_TEMP echo+
153.446014
unix% dmkeypar acisf01838_000N001_evt1.fits DATE-OBS echo+
2000-09-02T01:10:14
unix% dmkeypar acisf01838_000N001_evt1.fits TGAINCOR echo+
# dmkeypar (CIAO 3.4): ERROR: Keyword 'TGAINCOR' was not found in file 'acisf01838_000N001_evt1.fits
unix% dmkeypar acisf01838_000N001_evt1.fits CTI_CORR echo+
# dmkeypar (CIAO 3.4): ERROR: Keyword 'CTI_CORR' was not found in file 'acisf01838_000N001_evt1.fits
unix% dmkeypar acisf01838_000N001_evt1.fits CTI_APP echo+
# dmkeypar (CIAO 3.4): ERROR: Keyword 'CTI_APP echo+
# dmkeypar (CIAO 3.4): ERROR: Keyword 'CTI_APP' was not found in file 'acisf01838_000N001_evt1.fits
unix% dmkeypar acisf01838_000N001_evt1.fits ASCDSVER echo+
R4CU5UPD8.2
```

This is a -120 C observation taken in September 2000 that has not had the time-dependent gain or CTI corrections applied to it already. Also, this observation was processed before the TGAIN correction became part of SDP, i.e. the ASCDSVER is lower than DS 7.3.0. Note that the version naming convention changed after version R4CU5UPD14 to the "DS" system, starting with DS 6.0.0.

In many cases, the TGAIN calibration has been applied to the data, but the data should still be reprocessed to apply a newer version of the calibration. Refer to the <u>Calibration Updates</u> for a history of TGAIN calibration changes and the relevant observation dates.

Note that although the adjustment is currently only applicable to -120 C data, there are no adverse effects to running it on other data (the outcome is the same as if apply_tgain=no).

Related acis_process_events threads

There are other threads that should be considered, since they may affect how acis_process_events is run. The <u>Create a New Level=2 Event File thread</u> shows how to combine all of these options into a single run of acis_process_events.

- <u>Remove Pixel Randomization</u>
- <u>Apply/Remove PHA Randomization</u>

Generate A New Level=1 Event File

Determine the eventdef parameter

The <u>eventdef</u> parameter specifies the names and data types of the columns in the output event data file. Four predefined strings are included in the parameter file for acis_process_events:

READMODE	DATAMODE	event mode	eventdef string
TIMED	(V)FAINT	timed exposure (very) faint	stdlev1
TIMED	GRADED	timed exposure graded	grdlev1
CONTINUOUS	CC(33)_FAINT	continuous clocking (3x3) faint	cclev1
CONTINUOUS	CC(33)_GRADED	continuous clocking (3x3) graded	ccgrdlev1

If you are unsure of the event mode of your observation, the information can be found in the READMODE and DATAMODE values stored in the file header:

```
unix% <u>dmkeypar</u> acisf01838_000N001_evt1.fits READMODE echo+
TIMED
unix% dmkeypar acisf01838_000N001_evt1.fits DATAMODE echo+
FAINT
```

This is a timed exposure faint observation, so the proper eventdef parameter is "stdlev1." The full parameter syntax of each eventdef string may be found in <u>plist acis</u> process events.

Run acis_process_events

Running this tool with the <u>SDP</u> level=1 event file as the input will produce a *new* level=1 event file that has the latest CALDB applied. This means that the time–dependent gain correction will be applied.

The <u>apply_cti</u> parameter should *always* be set to yes, even if the data is already CTI-corrected. If it is set to no, the existing CTI correction is *removed*; see the <u>note on reapplying the CTI correction</u> for details.

```
unix% punlearn acis process events
unix% pset acis_process_events infile=acisf01838_000N001_evt1.fits
unix% pset acis_process_events outfile=acis_1838_new_evt1.fits
unix% pset acis_process_events badpixfile=acis_1838_new_bpix1.fits
unix% pset acis_process_events eventdef=")stdlev1"
unix% pset acis_process_events stop=none
unix% pset acis_process_events apply_tgain=yes
unix% pset acis_process_events apply_tgain=yes
unix% acis_process_events
Input event file or stack (acisf01838_000N001_evt1.fits):
Output event file name (acis_1838_new_evt1.fits):
aspect offset file ( NONE | none | <filename>) (NONE):
```

The <u>apply tgain</u> and <u>apply cti</u> parameters are both "on" by default (i.e. set to "yes"); the <u>pset</u> commands are used for emphasis in this example.

It is important to note the unusual syntax of the eventdef parameter; the tool will not access the predefined string if the leading ")" is missing (see example 6 of ahelp parameter).

The content of the parameter file may be checked using plist acis process events.

You may see a warning about the number of event islands that contain one or more bad pixels:

acis_process_events (CIAO 3.4): The following error occurred 26941 times: dsAFEBADPCNTERR -- WARNING: Event island contains 1 or more bad pixels.

It is explained in this FAQ and may be ignored.

Examining the Output

There are a few things that may be checked in order to confirm that the gain adjustment was applied. First, two new header keywords – TGAINCOR and TGAINFIL – have been created:

```
unix%dmlistacis_1838_new_evt1.fitsheadergrep TGAIN0078TGAINCORTString0123TGAINFILacisD2000-08-01t_gainN0006.fitsString
```

TGAINCOR is set to "T" for true. In the TGAINFIL case, the path to the CALDB is /soft/ciao/CALDB. If either of these keywords is missing or set to a different value ("F" or "none"), the gain adjustment was not applied.

Also, a PHA_RO column should exist in the output file and contain non-zero values:

unix% dmlist acis_1838_new_evt1.fits"[cols PHA_RO]" data rows="1:5"

Data for Table Block EVENTS				
ROW		pha_ro		
	1	249		
	2	273		
	3	138		
	4	2445		
	5	3660		

It is recommended that you keep this column in your data file (i.e. do not use a DM filter to remove it). These are the original (RO = readout) PHA values which are needed if you later want to rerun with new calibration.

Summary

This thread is now complete; the new level=1 event file is named acis_1838_new_evt1.fits. See the <u>final</u> section of the ACIS Gain Map thread to generate a new level=2 event file.

Parameters for /home/username/cxcds_param/acis_process_events.par

```
_____
#-
#
#
   acis_process_events.par- Parameter file for acis_process_events program
#
#
               _____
           infile = acisf01838_000N001_evt1.fits Input event file or stack
          outfile = acis_1838_new_evt1.fits Output event file name
     acaofffile = NONEaspect offset file ( NONE | none | <filename>)(apply_cti = yes)Apply CTI adjustment?apply_tgain = yes)Apply time-dependent gain adjustment?
   (apply_tgain = yes)
(alignmentfile = )acaofffile -> NONE) sim/fam alignment file ( NONE | none | <filename>)
     (obsfile = NONE)obs.par file for output file keywords ( NONE | none | <filename>)(geompar = geom)Parameter file for Pixlib Geometry files(logfile = stdout)debug log file ( STDOUT | stdout | <filename>)(gradefile = CALDB)grade mapping file ( NONE | none | CALDB | <filename>)(gainfile = CALDB)acis gain file ( NONE | none | CALDB | <filename>)
    (badpixfile = acis_1838_new_bpix1.fits) acis bad pixel file ( NONE | none | <filename>)
    (threshfile = CALDB)<br/>(ctifile = CALDB)split threshold file ( NONE | none | CALDB | <filename>)<br/>acis CTI file ( NONE | none | CALDB | <filename>)<br/>gain adjustment file ( NONE | none | CALDB | <filename>)
       (eventdef = )stdlev1 -> {d:time,s:ccd_id,s:node_id,i:expno,s:chip,s:tdet,f:det,f:sky,s:phas,l:pha,l:pl
                                  Determine event flight grade?
Check very faint pixels?
Estimate the times of arrival for CC-mode observation?
Trail fraction
Default split threshold level (overridden by values in threshfile)
Offset to add to event time field to symph w/ for data
f:energy,l:pi,s:fltgrade,s:grade,x:status}) output format definition
    (doevtgrade = yes)
 (check_vf_pha = no)
(calc_cc_times = no)
           (trail = 0.027)
       (spthresh = 13)
   (time_offset = 0)
```

(docentroid = no)	Determine pixel centroid for coord. conversion?
(calculate_pi = yes)	perform pha->pi conversion? (requires gain file)
$(pi_bin_width = 14.6)$	Width of Pi bin in eV
(pi_num_bins = 1024)	Number of values to bin energy into
(max_cti_iter = 15)	Maximum iterations for the CTI adjustment of each event
(cti_converge = 0.1)	The convergence criterion for each CTI-adjusted pixel in adu
(tstart = TSTART)	header key containing start/default time value
(tstop = TSTOP)	header key containing time of last event
(clobber = no)	Overwrite output event file if it already exists?
(verbose = 0)	level of debug detail (0=none, 5=most)
(stop = none)	where to end transformations
(instrume = acis)	axaf instrument- used for instrument parameter file
$(rand_seed = 1)$	random seed (for pixlib), $0 =$ use time dependent seed
(rand_pha = yes)	Randomize the pha value used in gain calculations
(rand_pix_size = 0.5)	pixel randomization width (-size+size) 0=no randomization
	.,s:node_id,i:expno,s:chip,s:tdet,f:det,f:sky,s:phas,l:pha,l:pha_ro,
· · · · · · · · · · · · · · · · · · ·	faint modes event definition string
•	,s:node_id,i:expno,s:chip,s:tdet,f:det,f:sky,l:pha,s:corn_pha,f:ene
· · · · · · · · · · · · · · · · · · ·	graded event format definition string
•	.s:node_id,i:expno,s:chip,s:tdet,f:det,f:sky,f:sky_1d,s:phas,l:pha,
	x:status}) CC faint event format definition string
	,s:node_id,i:expno,s:chip,s:tdet,f:det,f:sky,f:sky_1d,l:pha,f:energ
· · · · · · · · · · · · · · · · · · ·	graded event format definition string
(mode = ql)	

History

16 Dec 2004	updated for CIAO 3.2; use ACIS bad pixel file (badpixfile parameter)
01 Feb 2005	added note about "Event island contains 1 or more bad pixels" warning
23 Jun 2005	CIAO 3.2.2 patch: new calibration files in CALDB 3.1.0; minor acis_process_events parameter change (default value of <u>threshfile</u> is CALDB instead of NONE)
12 Dec 2005	updated for CIAO 3.3: new time-dependent gain files in CALDB 3.2.0; output filenames include ObsID
14 Jun 2006	update to calibration info: new TGAIN files released in CALDB 3.2.2
07 Nov 2006	update to calibration info: new TGAIN files released in CALDB 3.2.4
18 Dec 2006	updated for CIAO 3.4: new calibration files in CALDB 3.3.0; include CTI_APP in keyword checks; removed use of "rand_pha=no" in acis_process_events, as most users should keep the PHA randomization (see the <u>Apply/Remove PHA Randomization thread</u>); CIAO version in errors
01 May 2007	updated for CALDB 3.4.0: TGAIN files for August 2006 – April 2007
21 May 2007	need to set <u>stop=none</u> if aspect solution is not provided
14 Sep 2007	updated for CALDB 3.4.1: TGAIN files for May 2007 - July 2007
14 Dec 2007	updated for CALDB 3.4.2: TGAIN files for August 2007 – October 2007
31 Mar 2008	updated for CALDB 3.4.3: new -120 C TGAIN files and first -110 C TGAIN file

URL: http://cxc.harvard.edu/ciao/threads/acistimegain/

Last modified: 31 Mar 2008