



Creating ACIS RMFs with mkacisrmf

Return to: [Why Index](#)

[Analysing Data](#) | [Using Consistent Calibration](#) | [Technical Details](#) | [Figures](#)

Analysing Data

Instructions on how to run this tool are given in the [mkacisrmf analysis thread](#).

The tool [mkacisrmf](#) is used to create RMFs for:

- all –120 ACIS data taken in (V)FAINT mode that has the [time-dependent gain adjustment](#) and [CTI correction](#) applied
- –120 ACIS GRADED mode data on the back-illuminated chips (ACIS–S1 and S3) only that has the [time-dependent gain adjustment](#) applied
- –110 ACIS data taken on the back-illuminated chips (ACIS–S1 and S3) only that has the [time-dependent gain adjustment](#) applied

*All new analyses with these types of data should be done with **mkacisrmf** instead of **mkrmf**.* The results from [mkacisrmf](#) and [mkrmf](#) are very similar, except for the following cases:

- The new RMFs are 10–15% more accurate at energies lower than 1 keV.
- Calibration for the ACIS–S1 (`ccd_id=5`) back-illuminated chip has been greatly improved.

Scripts: [specextract](#) and [psextract](#)

There are specific cases when [mkacisrmf](#) may be used in conjunction with the [specextract](#) or [psextract](#) scripts to create more accurate RMF files. Refer to the appropriate section of the [mkacisrmf](#) thread for more information:

- [Using mkacisrmf with the specextract script](#)
- [Using mkacisrmf with the psextract script](#)

[Figure 1](#) and [Figure 2](#) also illustrate when to use [mkrmf](#) versus [mkacisrmf](#).

Using Consistent Calibration

The calibration applied to the event file must be consistent with the RMF tool chosen or a systematic energy shift will occur.

–120 C Data: [mkacisrmf](#)

For data taken at the [–120 C focal plane temperature](#), the newest gain file is automatically selected when [acis_process_events](#) is run. The [CTI](#) and [TGAIN](#) corrections must also be applied when reprocessing the data. There is [TGAIN](#) calibration for GRADED mode data, but no [CTI](#) correction.

```
acisD2000-01-29gain_ctiN0006.fits
```

Note that any file *since version 4* (*gain_ctiN0004*) is "good enough" for use with `mkacisrmf`.

–120 C Data: `mkrmf`

If you wish to finish an analysis using `mkrmf`, you must process the data with the version 2 gain file (`acisD2000-01-29gain_ctiN0002.fits`). Set the `gainfile` parameter to:

```
unix% pset acis_process_events \  
gainfile=$CALDB/data/chandra/acis/bcf/gain/acisD2000-01-29gain_ctiN0002.fits
```

–110 C Data

For data taken at the –110 C focal plane temperature on the back-illuminated chips (ACIS–S1 and S3), the appropriate gain file is automatically selected when `acis_process_events` is run. The TGAIN correction must also be applied when reprocessing the data; there is no CTI available for –110 C.

```
acisD1999-09-16gainN0006.fits
```

Analysis for the –110 C front-illuminated chips must still be done with `mkrmf`.

Technical Details

The `mkacisrmf` tool contains all the functionality of the previous tool `mkrmf`. Unlike its predecessor, however, `mkacisrmf` separates the RMF calculation process into two components: an "ideal" component which describes the CCD spectral response prior to the effects of CTI, and a spatially varying component which incorporates the changes in the response produced by CTI.

This new method was motivated primarily by a desire to provide a more rapid means of developing ACIS response calibration products. Accompanying the new tool is a new CCD analysis reference data (ARD) file which describes both the ideal response and the spatial variation produced by CTI. In contrast to traditional CCD FEFs, the CTI-induced spatial variations can be generated directly from numerical simulations of the CCD response obviating the need for laborious fitting at each position on the CCD. This human-intensive fitting was the primary bottleneck in generating ACIS FEFs. Once the "scatter matrix", describing the spatial variations, has been generated automatically, small scale adjustments are included to account for differences between the simulated response and the actual CCD response as measured using data from the onboard calibration source.

The algorithm contained in `mkacisrmf` is based upon the the algorithm in Alexey Vikhlinin's tool `calcrmf2`, which is described in his memo "Updates to the RMF model in the ACIS FI CCDs" (PDF). The CIAO tool is essentially a direct translation of this prototype code and includes a number of enhancements including an improved interpolation scheme to calculate the response at intermediate energies between the available calibration points. All functionality of the previous tool `mkrmf` is available including the ability to produce weighted response matrices for arbitrary spatial regions.

Figures

Creating ACIS RMFs – CIAO 3.4




Figure 1. Using mkrmf in an analysis thread.




Figure 2. Using mkacisrmf in an analysis thread.

The Chandra X-Ray Center (CXC) is operated for NASA by the Smithsonian Astrophysical Observatory.
60 Garden Street, Cambridge, MA 02138 USA.
Smithsonian Institution, Copyright © 1998–2008. All rights reserved.

URL:
<http://cxc.harvard.edu/ciao3.4/why/mkacisrmf.html>
Last modified: 20 March 2008

