Fitting PHA Data with Multi–Component Source Models



Sherpa Threads (CIAO 3.4)

Table of Contents

- <u>Getting Started</u>
- <u>Reading Data & Instrument Responses Into Sherpa</u>
- <u>Filtering Spectral Data</u>
- Establishing Model Components
- Defining a Multi-Component Source Model Expression
- <u>Modifying Method & Statistic Settings</u>
- <u>Fitting</u>
- Examining Fit Results
- <u>Checking Sherpa Session Status</u>
- Saving a Sherpa Session
- <u>Using Sherpa Scripts & Restoring a Session</u>
- <u>Summary</u>
- <u>History</u>
- Images
 - ◆ Source spectrum (0.5–8.0 keV)
 - Power-law + absorption fit with residuals
 - ♦ <u>Default parameters for the confidence region</u>
 - Confidence region as a contour plot

Fitting PHA Data with Multi–Component Source Models

Sherpa Threads

Overview

Last Update: 1 Dec 2006 - reviewed for CIAO 3.4: no changes

Synopsis:

This thread shows how to do a basic spectral fit with the appropriate response files. If you are interested in including the background in the fit as well, see the <u>Independent Background Responses</u> thread.

Proceed to the <u>HTML</u> or hardcopy (PDF: <u>A4 / letter</u>) version of the thread.

Getting Started

Please follow the "Sherpa Threads: Getting Started" thread.

Reading Data & Instrument Responses Into Sherpa

In this thread, we wish to fit spectral data from the FITS PHA datafile source_pi.fits. This dataset is input into *Sherpa* with the <u>READ</u> command:

```
sherpa> DATA source_pi.fits
The inferred file type is PHA. If this is not what you want, please
specify the type explicitly in the data command.
WARNING: statistical errors specified in the PHA file.
    These are currently IGNORED. To use them, type:
        READ ERRORS "<filename>[cols CHANNEL,STAT_ERR]" fitsbin
```

Note that the READ DATA command may be shortened to just <u>DATA</u>.

Now the dataset may be plotted:

sherpa> <u>LPLOT</u> DATA

Note that these data are plotted in bin (i.e. channel) space, because there is no information about RMF/ARF attached to the header of this file. A standard PHA file contains number of counts in each PHA channel, which *Sherpa* reads. Therefore only counts per channel will be plotted with the above command. For details on *Sherpa* plotting see <u>Data Visualization</u> thread.

Fitting PHA Data with Multi-Component Source Models

Fitting PHA Data – Sherpa

In order to assign the instrument properties (such as for example RMF and ARF files) an instrument model has to be defined. The *Sherpa* model name for an instrument response model, defined by the standard instrument response files, is <u>RSP</u>. The <u>RSP</u> model component is established for use and is named acis:

```
sherpa> <u>RSP</u>[acis]
acis.rmf parameter value ["none"] rmf.fits
acis.arf parameter value ["none"] arf.fits
The inferred file type is ARF. If this is not what you want, please
specify the type explicitly in the data command.
```

Notice that in the square bracket we named the response model as acis. *Sherpa* prompts the user for input of the model's default parameter values, e.g. two filenames for rmf and arf. Because the parameters belong to the acis model they are named acis.rmf and acis.arf. We set the rmf and arf parameter values to the proper <u>RMF</u> and <u>ARF</u> filenames for this dataset. It is possible, however, to establish a response model using *only* an RMF *or* an ARF file.

In order to assign acis model to the data and convolve the PHA data with the response, the instrument model has to be defined. Note that this allows for multiple models to be established during the *Sherpa* session, while only the one assigned to instrument used during fitting.

sherpa> <u>INSTRUMENT</u> = acis

The current definition of *Sherpa*'s instrument model may be examined using <u>SHOW</u> INSTRUMENT:

sherpa> <u>SHOW</u> INSTRUMENT						
Instrument 1: rspld[acis]						
Param Type Value						
1	rmf	string:	"rmf.fits"	(N_E=198,N_PHA=1024)		
2	arf	string:	"arf.fits"	(N_E=495)		

This output shows that rmf.fits and arf.fits currently define the instrument model. Check<u>RSP</u> for requirement on the binning in RMF and ARF files.

The input dataset may be plotted again:

sherpa> <u>LPLOT</u> DATA

The data are now plotted in energy space since the instrument model is providing the information necessary for the computation of the number of predicted counts in each energy bin.

Filtering Spectral Data

Sherpa has many filtering options with <u>IGNORE</u> and <u>NOTICE</u> commands. During this *Sherpa* session, we would like to fit only the data between 0.5 and 8.0 keV. To apply this filter to the dataset:

```
sherpa> <u>IGNORE</u> ENERGY :0.5, 8:
```

Note: this command may be entered only after an instrument model has been defined.

To remove this filter:

sherpa> <u>NOTICE</u> ALL

Fitting PHA Data – Sherpa

The filter may then be re–applied (or a different filter may be applied):

sherpa> <u>IGNORE</u> ENERGY :0.5, 8:

The filtered dataset may then be plotted:

sherpa> <u>LPLOT</u> DATA

Figure 1 to shows the resulting plot. Notice that the plot now includes only the data in the specified energy region.

Establishing Model Components

We will fit the spectral data using a source model expression that involves multiple model components.

The first of these model components is the one-dimensional power-law model, <u>POWLAW1D</u>. The <u>POWLAW1D</u> model component is established and is named p1 defined in the square bracket:

```
sherpa> <u>PARAMPROMPT</u> OFF
Model parameter prompting is off
sherpa> <u>POWLAW1D</u>[p1]
```

Since a dataset has been input, *Sherpa* estimates the initial parameter values (and the minimum and maximum for their ranges) for this model based on the data. The command <u>PARAMPROMPT</u> OFF cancels prompting for immediate changes to these model parameter value estimates.

The second of the model components is the XSpec photoelectric absorption model, called <u>XSWABS</u> in *Sherpa*. Please see the <u>XSpec User's Guide</u>, or <u>ahelp xs</u>, or <u>ahelp xswabs</u> for more information about this model. Note that all XSpec models are available from within *Sherpa* and their XSpec names must be preceded by XS.

The <u>XSWABS</u> model component is established and is named abs1:

sherpa> <u>XSWABS</u>[abs1]

Again, since a dataset has been previously input, Sherpa estimates the initial parameter values based on the data.

Defining a Multi-Component Source Model Expression

We will now fit the spectral data using an expression that is the product of the model components established above. The <u>SOURCE</u> defines the final model expression used for fitting the data:

sherpa> <u>SOURCE</u> = abs1*p1

The current definition of *Sherpa*'s source model expression including initial parameter values for each model component may be examined using <u>SHOW_SOURCE</u>:

```
sherpa> <u>SHOW</u> SOURCE
Source 1: (abs1 * p1)
xswabs[abs1] (XSPEC model name: absw) (integrate: off)
Param Type Value Min Max
```

Units

1	nH	thawed	1e-01	1e-07	10	10^22/cm^2
pow	law[p1]] (inte	egrate: on)			
	Param	Type	Value	Min	Max	Units
1	gamma	thawed	1	-10	10	
2	ref	frozen	1	0.5183	7.9789	
3	ampl	thawed	7.1163e-06	7.1163e-08	7.1163e-04	

This output shows that abs * pl is currently defined as the source model expression. By default, integration over an energy bin is turned off for the abs1 model component and is turned on for the pl model component. However, since we are using a multiplicative source model expression to fit binned PHA data, integration of source expression over each energy bin *will* be performed during fitting.

Modifying Method & Statistic Settings

The <u>SHOW</u> command may be used to view the current method and statistics settings:

she Opt	erpa> <u>SHOW</u> timization	METHOD Method: Le	evenberg-Mar	quardt			
	Name	Value	Mir	n Max	Description		
				·			
1	iters	2000	1	. 10000	Maximum number of iterations		
2	eps	1e-03	1e-09) 1	Absolute accuracy		
3	smplx	0	C) 1	Refine fit with simplex (0=no)		
4	smplxep	1	1e-04	1000	Switch-to-simplex eps factor		
5	smplxit	3	1	. 20	Switch-to-simplex iters factor		
she	sherpa> <u>SHOW</u> STATISTIC						
Statistic:			ni-Squared G	Sehrels			

We will change the statistic to <u>Cash</u> for fitting this data:

sherpa> <u>STATISTIC</u> CASH

Note that <u>truncation</u> is turned on when the Cash statistic is used. This setting prevents negative model–predicted data values from affecting the convergence process.

Further details about the Levenberg–Marquardt optimization method which is the default method in *Sherpa* are available by typing:

sherpa> <u>ahelp lev-mar</u>

Fitting

The dataset is then fit:

```
sherpa> <u>FIT</u>
WARNING: the Levenberg-Marquardt optimization method works
less robustly when the Cash or cstat statistic is used.
Consider using the Powell or Simplex method instead.
```

Notice that the first warning recommends that we use a different optimization method. Before refitting the data, we reset the initial parameter values and switch to the Powell method:

sherpa>	<u>RESET</u>	
sherpa>	<u>METHOD</u>	POWEL

And now run the fit again:

The new warning refers to the final value of the amplitude parameter being to close to the boundary. We will expand allow min/max range for this parameter and refit. First, we examine the current parameter values for the model p1:

sherpa> <u>SHOW</u> p1							
<pre>powlaw[p1] (integrate: on)</pre>							
	Param	Туре	Value	Min	Max	Units	
1	gamma	thawed	0.8154	-10	10		
2	ref	frozen	1	0.5183	7.9789		
3	ampl	thawed	7.1163e-04	7.1163e-08	7.1163e-04		

As noted in the warning, we change the Max setting for the amplitude (pl.ampl):

sherpa> pl.ampl.max = 0.1

And fit the data a final time:

Use <u>LPLOT</u> to plot the fit and residuals. Also see <u>Customizing Sherpa plots</u> thread to learn how to use Slang to make nice plots.

7

```
sherpa> LPLOT 2 FIT RESIDUALS
==> Error bars computed using Chi Gehrels.
==> Error bars computed using Chi Gehrels.
sherpa> PRINT POSTFILE sherpa.spectra.2.ps
```

Figure 2 to shows the resulting plot. The features seen in the residuals could be due to the real source emission being different than the assumed power law model. This is in fact true for our data set. The spectrum is from a supernova remnant usually characterized by thermal emission accompanying with several emission lines. Also some features could be due to calibration uncertainties. We do not discuss further analysis here, which in normal data analysis process would consist of changing the source expression to include preferable plasma emission model and refiting.

Examining Fit Results

Several algorithms are available in *Sherpa* for examining fit results such as <u>covariance</u>, <u>projection</u>, <u>uncertainty</u>, <u>interval-projection</u>, <u>region-projection</u> A detailed description of how to use different options is available in several threads: <u>Step-by-Step Guide to Estimating Errors and Confidence Levels</u> and <u>Estimating Errors and Confidence Levels</u>. Also *Sherpa* S-lang module functions allows for easy access to the results in both scripts and on the command line. They are described in <u>Accessing fit results using S-Lang</u> thread.

Checking Sherpa Session Status

The final overall status of this Sherpa session may be viewed as follows:

```
sherpa> SHOW
Optimization Method: Powell
Statistic:
             Cash
Input data files:
        _____
Data 1: source_pi.fits pha.
Total Size: 1024 bins (or pixels)
Dimensions: 1
Total counts (or values): 3328
Exposure: 7854.47 sec
Count rate: 0.424 cts/sec
  Backscal: 2.366406e-06
Current filters for dataset 1:
notice source 1 all
IGNORE source 1 ENERGY : 0.5 , 8 :
Noticed filter size: 512 bins
Sum of data within filter: 3283
Defined analysis model stacks:
```

```
source 1 = (abs1 * p1)
instrument source 1 = acis
Defined source/background model components:
powlaw[p1] (integrate: on)
   Param Type Value Min Max
                                                                      Units

      1
      gamma thawed
      1.5009
      -10
      10

      2
      ref frozen
      1
      0.5183
      7.9789

      3
      ampl thawed
      2.0049e-03
      7.1163e-08
      1e-01

                                                                       ____
xswabs[abs1] (XSPEC model name: absw) (integrate: off)
  Param Type Value Min Max
                                                                      Units
                      _____
                                                ----
       ---
                                    ___
                                                                      ____
1 nH thawed 2.3776 1e-07
                                                10 10^22/cm^2
Defined instrument model components:
 _____
rspld[acis]
  Param Type Value
    ____
            ____
                   ____
   rmf string: "rmf.fits" (N_E=198,N_PHA=1024)
1
2 arf string: "arf.fits" (N_E=495)
```

Saving a Sherpa Session

To save a Sherpa session so that we may return again later, use the **SAVE** command:

```
sherpa> <u>SAVE</u> ALL session1.shp
sherpa> <u>EXIT</u>
```

where session1.shp is the filename for an ASCII file to which a record the current session will be written, in the form of a *Sherpa* script.

Using Sherpa Scripts & Restoring a Session

Sherpa commands may either be issued on the Sherpa command line or from a file by the USE command.

To restore the session that was saved to the file session1.shp:

```
sherpa> USE session1.shp
The inferred file type is ARF. If this is not what you want, please
specify the type explicitly in the data command.
The inferred file type is PHA. If this is not what you want, please
specify the type explicitly in the data command.
WARNING: statistical errors specified in the PHA file.
        These are currently IGNORED. To use them, type:
```

```
READ ERRORS "<filename>[cols CHANNEL,STAT_ERR]" fitsbin
WARNING: model truncation turned on. Override with TRUNCATE OFF.
sherpa>
```

One may verify that the session has been properly restored by comparing the <u>SHOW</u> output from the <u>Checking</u> <u>Sherpa Session Status</u> section.

Summary

This thread is complete, so we can exit the Sherpa session:

sherpa> <u>EXIT</u> Goodbye.

History

14 Jan 2005 reviewed for CIAO 3.2: no changes

21 Dec 2005 reviewed for CIAO 3.3: no changes

01 Dec 2006 reviewed for CIAO 3.4: no changes

URL: http://cxc.harvard.edu/sherpa/threads/spectra/

Last modified: 1 Dec 2006



Image 1: Source spectrum (0.5-8.0 keV)



Image 2: Power-law + absorption fit with residuals



Image 3: Default parameters for the confidence region





1.2

2

2.2

2.4

abs1.nH

2.6

2.8