

URL: http://cxc.harvard.edu/ciao3.4/faq/dp hrc pha.html Last modified: 26 October 2007

## Why do the HRC-S threads filter out the final PHA channel (e.g. "pha=0:254")?

PHA has 256 channels (0 to 255). Filtering PHA 0:254 (i.e. removing channel 255) is a quick way to remove a fair amount of HRC–S background. Roughly 30% of background events and ~0% of x-ray events have PHA=255. You can safely remove PHA=0, too, but the improvement is negligible. See the <u>HRC–S Degap</u> Correction thread for an example of this filtering.

For grating data, better results are obtained when using the LETG/HRC-S "light" background filter, as described in the <u>Apply background filter section</u> of the <u>Obtain Grating Spectra from LETG/HRC-S Data</u> thread. This uses a PHA filter (actually, a PI filter) centered on the expected mean PI value as a function of LETG/HRC-S dispersed wavelength. A tighter filter can therefore be used. This not only removes a larger fraction of the background, it does so more uniformly than simply removing pha=255 (which is not adjusted for local gain variations, as PI is). This may be important when doing spectral background subtractions.

The Chandra X–Ray Center (CXC) is operated for NASA by the Smithsonian Astrophysical Observatory. 60 Garden Street, Cambridge, MA 02138 USA. Smithsonian Institution, Copyright © 1998–2006. All rights reserved.

URL: http://cxc.harvard.edu/ciao3.4/faq/dp\_hrc\_pha.html Last modified: 26 October 2007 FAQ Entry – CIAO 3.4